

Table of Contents

O	view	
	Email Providers	3
	Gmail - Advanced Options Setup	
	Yahoo - Advanced Options Setup	7
	AOL - Advanced Ontions Setup	2



Overview

If you do not see your email provider listed below, you will need to contact your email provider for assistance with providing the required information necessary to complete this worksheet. If your email provider is listed, please click their name to see the settings AVImark will need to be able to email.



AVImark is not compatible with all email providers. The ability to use this function of AVImark will depend on the version of AVImark and the email provider. For example, Gmail will not work with versions below 2010 and Microsoft® will not work with any version of AVImark due to incompatibility with their settings.

When asking for the information for email setup, please let the email provider know you need settings for Microsoft Outlook®.

Email Providers

<u>Gmail</u>™ <u>Yahoo!</u>® <u>AOL</u>®

- 1. On the speed bar, click on the Wrench (🧪) icon. This will bring up the Advanced Options.
- 2. In the search box type in e-mail. This will bring up the options you will need to modify.



If you see any Site values and you are not running Site, you will want to remove those values from the E-Mail Advanced Options. To remove a value, right-click | Remove.

- **Disconnect Between Sending E-mails.** This should be set to True if your email provider has a cap or limit of how many emails can be sent at one time or per batch.
- Number of E-Mails to send to client at one time. If Disconnect Between Sending E-mails is set to True, you will need to put a value under what your cap is. Example: If you can send out an email with 100 recipients at one time, you would want to put a value around 80 in this field. If Disconnect Between Sending E-mails is False, you can skip this step.

```
Options Maintenance

File Edit View Help

Search e-mail

Reminders

E-mail

System

-E-mail Error Messages

-mail

Disconnect Between Sending E-mails

Number Of E-mails To Send To Client At One Time

Reply E-mail Address

Use E-mail Client

Use Reply To E-mail for From E-mail

POP

SMTP
```



Reply E-Mail Address. This will be the email address you want your customers to reply
to if they email you back.



Some email providers require this to be your username. If you receive errors when trying to email, try your username in this option.

• Use E-Mail Client. If this option is set to True, AVImark will use the default email client of the computer. (i.e. Microsoft Outlook, Mozilla Thunderbird) to send emails. This will allow you to work with any email provider if AVImark is having trouble sending emails and may work great for sending single emails. However, if you are sending out mass emails; such as, reminders or newsletters, these options need to be set to False.

POP SETTINGS


- Password: The password that you use to access your email.
- 2. POP Port: The port number of the mail server AVImark will connect when sending email. Most of the time, the port is 110.



- Server Name: The server that transfers incoming mail sent to your email account. Most of the time it is going to be pop.servicesprovider.com. For instance, Gmail's POP server is pop.gmail. com.
- **4. Use Secure Connection**: This option enables SSL or TLS, if needed.
- User Name: The name that you provide when accessing your mail account. Example: user or user@mail.com.

SMTP SETTINGS

- Password: The password that you use to access your email.
- 2. POP Before SMTP: Some mail servers must check for new email before sending out mail. If the preceding circumstance applies, this option should be set to True. If False, you can skip steps 5-6.





- **3. Server Name**: The server that sends outgoing email from your email account. Most of the time it is going to be smtp.servicesprovider.com. For instance, Gmail's SMTP server is smtp.gmail.com.
- 4. Server Requires Login: This option causes AVImark to provide the mail server with a username and password before an email is sent. Note: If you have a username and password, this option should be set to True.
- **5. SMTP Port**: The port number of the mail server AVImark will connect when sending email. Most of the time the port is 25.
- **6.** Use Secure Connection: This option enables SSL or TLS, if needed.
- 7. **User Name**: The name that you provide when accessing your web mail account or the SMTP server user name in the email account settings of your email client application.



Gmail - Advanced Options Setup

	Option	Defaul	lt Value
	Disconnect between Sending E-mails	True	
Email	Number of E-mails to Send to Client at One Time	50	
	Reply E-mail Address	The email address yo reply to with any que	
	Password	leave blank*	
	POP Port	leave blank*	
POP	Server Name	leave blank*	
	Use Secure Connection	Never	
	User Name	leave blank*	
	Password	your Gmail password	*
	POP before SMTP	False	
	Server Name	smtp.gmail.com	
SMTP	Server Requires Login	True	
SMIP	SMTP Port and Secure Connection Settings	ver 2018 or newer	prior to ver 2018
	SMTP Port	587	465
	Use Secure Connection	TLS	SSL
	User Name	your Gmail address*	



*If you see any Site values and are not using the Site feature, you will want to remove those values from the E-Mail advanced options. To remove, highlight on the entry and do a right-click | Remove. You can verify this by checking that <No data to display> appears at the bottom of the window when an option is highlighted.



Yahoo - Advanced Options Setup

Yahoo Email Limit: no more than 100 emails or recipients per hour.

	Option	Defaul	t Value
	Disconnect between Sending E-mails	True	
Email	Number of E-mails to Send to Client at One Time	50	
	Reply E-mail Address	Full Yahoo email addr	ress*
	Password	leave blank*	
	POP Port	leave blank*	
POP	Server Name	leave blank*	
	Use Secure Connection	Never	
	User Name	leave blank*	
	Password	your Yahoo password	*
	POP before SMTP	False	
	Server Name	smtp.mail.yahoo.com	
CLATE	Server Requires Login	True	
SMTP	SMTP Port and Secure Connection Settings	ver 2018 or newer	prior to ver 2018
	SMTP Port	587	465
	Use Secure Connection	TLS	SSL
	User Name	Full Yahoo email addr	ress*



*If you see any Site values and are not using the Site feature, you will want to remove those values from the E-Mail advanced options. To remove, highlight on the entry and do a right-click | Remove. You can verify this by checking that <No data to display> appears at the bottom of the window when an option is highlighted.



AOL - Advanced Options Setup

	Option	Defaul	lt Value
	Disconnect between Sending E-mails	True	
Email	Number of E-mails to Send to Client at One Time	50	
	Reply E-mail Address	Full AOL email addres	SS*
	Password	leave blank*	
	POP Port	995	
POP	Server Name	leave blank*	
	Use Secure Connection	Never	
	User Name	leave blank*	
	Password	your AOL password*	
	POP before SMTP	False	
	Server Name	smtp.verizon.net	
CMTD	Server Requires Login	True	
SMTP	SMTP Port and Secure Connection Settings	ver 2018 or newer	prior to ver 2018
	SMTP Port	587	465
	Use Secure Connection	TLS	SSL
	User Name	Full AOL email addres	ss*



*If you see any Site values and are not using the Site feature, you will want to remove those values from the E-Mail advanced options. To remove, highlight on the entry and do a right-click | Remove. You can verify this by checking that <No data to display> appears at the bottom of the window when an option is highlighted.

